

ACME FlowMaster 3000 - Modbus Register Map

Document rev 1.2

Register addresses use the Modicon convention: 4xxxx = holding registers, 3xxxx = input registers, 0xxxx = coils. 32-bit values are big-endian (high word first). Slave/Unit ID 1.

Register	Description	Type	Scale	Unit	Access	Notes
40001	Ramp Counter	UINT16	1	-	R	Test ramp, increments by 10
40011	Supply Temperature	UINT16	0.1	°C	R	e.g. 100 = 10.0 C
40101	System Pressure	FLOAT32	1	bar	R	IEEE754, 2 registers
40111	Energy Total	UINT32	1	kWh	R	2 registers, hi word first
30001	Raw Sensor Input	UINT16	1	counts	R	Input register
00001	Pump Command	BOOL	-	-	R/W	0 = Off, 1 = On

Pump Command enumeration: 0 = Off, 1 = On. All holding registers are read/write unless marked R.